





*Huron Landscaping Limited*

## HOW TO PLANT A CONIFER OR DECIDUOUS TREE FROM HURON LANDSCAPING LIMITED



**Deciduous Tree**



**Conifer Tree**

**Nursery and Garden Shop  
location  
1/2 mile - South of Lucknow**


1. Read planting instructions carefully. It is easier to plant a tree with two people. **YOUR PLANTS LIFE DEPENDS ON YOU!**
2. Select a site to plant your tree away from roof drains, water swales, septic systems, and wet areas.
3. It is recommended to prune 1/3 of each branch of the head off the tree with a sharp pair of pruners when planting.
4. Dig hole twice as large as the ball or pot. A minimum of 20" deep and 36" in diameter is essential.
5. Partly refill the hole with a good planting loam mixture consisting of 1/3 Fafard Peat Moss, 1/3 Hillview Cattle Manure and 1/3 good Top Soil, thoroughly blended together.
6. Remove pot and place plant into prepared hole to ensure proper depth. Compact soil under plant until the bottom of graft or bud union is approx. 1 1/2" above existing grade. Place your steel T-bar or wooden 2" x 2" stake across top of hole. Top of stake is correct height for the bottom of bud union or graft.
7. Lift plant out and carefully place beside hole.
- 8A. **FOR BALLED AND BURLAPPED TREES:** Do not remove burlap. Delete Step 7. Simply open the knot and loosen around the trunk and fold down top 1/3 of burlap. Go to step 10.
- 8B. **FOR TREES WITH PAPER MACHE POTS:** Remove pot completely. Repeat 8C.
- 8C. **FOR TREES WITH PLASTIC OR METAL CONTAINERS:** Carefully remove the pot trying to keep the root ball intact.
- 8D. **FOR BARE ROOT TREES:** One person holds tree while the other person spreads out the roots cutting off any broken roots.
9. Set unpotted plant back into the hole to correct depth.
10. Backfill balance of the hole with soil mixture in 5. Compact soil firmly around the roots with heel or toe as you backfill. Leave a slight depression around the trunk of the tree. **ALL GRAFTS AND BUD UNION MUST BE ABOVE GROUND.**
11. Stake tree using Steel T-bar and Tree Collar or wooden 2" x 2" stake with rubber hose and wire.
12. **SOAK THOROUGHLY** — apply water at the base of the plant at a slow rate until the water will not soak in anymore. Repeat this procedure at least two or three times in the next two days after planting.
13. Apply mulch of Peat Moss or Bark Chips to keep soil from drying out.
14. **MOST IMPORTANT:** Do not allow the ground to dry out. Lack of water will cause your tree to dry out! Over watering will cause new roots to rot and eventually kill the tree. **WATER CAREFULLY WHEN REQUIRED DURING THE GROWING SEASON.**
15. Be sure your tree does not go into winter in a dry condition. Water well before the ground freezes.
16. Spray your tree for insect disease control, as required with CIL Tree & Shrub Spray. Use CIL Leafminer Killer for birch trees.
17. For Fruit Trees, a Dormant spray in late March, followed by 7-8 sprayings of Fruit Tree Spray will give maximum protection.
18. **NOTE:** Do not plant another tree or shrub under the canopy of a black walnut tree.



Huron Landscaping Limited

## HOW TO PLANT AN EVERGREEN

### FROM HURON LANDSCAPING LIMITED



Evergreen  
Foundation Planting



1. Read planting instructions carefully. **YOUR PLANTS LIFE DEPENDS ON YOU!**
2. Select a site suited to the plants you have purchased. Good drainage is required for successful results.
3. Remove sod from planting bed. Loosen top soil 10" - 12" in depth (A roto-tiller makes this job easy). If soil is poor, excavate and remove.
4. Add a good top soil mixture of 1/3 Peat Moss, 1/3 Hillview Cattle Manure and 1/3 clean Top Soil thoroughly blended together. Planting bed should be 3" - 4" above lawn.
5. Dig a hole twice as large as the pot, approximately 15" deep and 24" in diameter.
6. Partly refill hole with mixture from 4. Set plant into hole at correct depth.
7. **FOR PLANTS WITH BROWN PAPER MACHE POTS:** Lift plant carefully from hole, remove and place root ball about 2" below final grade.
8. **FOR PLANTS IN PLASTIC OR METAL CONTAINERS.** These plants are container grown. **CAREFULLY** remove the pot, keeping the root ball intact. Place back in to hole at correct depth.
9. Backfill balance of hole with soil mixture in 4. Compact soil firmly around the roots with heel or toe as you backfill. Leave a slight depression around the trunk for water.
10. **SOAK THOROUGHLY** — apply water at the base of the plant at a slow rate until the water will not soak in anymore. Repeat this procedure at least two or three times in the next two days.
11. Applying a mulch of your choice to planting bed will keep soil from drying out and reduce watering.
12. **MOST IMPORTANT:** Do not allow the ground to dry out. Lack of water will cause your plant to dry out! Over watering will cause net roots to rot and eventually kill the plant. **WATER CAREFULLY WHEN REQUIRED DURING THE GROWING SEASON.**
13. Be sure your plant does not go into winter in dry condition. Water well before the ground freezes.
14. Spray your Evergreens for insect control with CIL Tree and Shrub Spray or CIL Ornamental Insect Killer as required.
15. **IF IN DOUBT, ASK ANY NURSERY SALES PERSON FOR THE CORRECT PRODUCT.**
16. **NOTE:** Do not plant another tree or shrub under the canopy of a black walnut tree.